

### **Economic and Social Council**

Distr.: General 2 July 2021

Original: English

### **Economic Commission for Europe**

**Inland Transport Committee** 

Working Party on Customs Questions affecting Transport

Group of Experts on Conceptual and Technical Aspects of Computerization of the TIR Procedure

Third session

Geneva, 13–15 September 2021 Item 4 (d) of the provisional agenda eTIR conceptual, functional and technical documentation version 4.3: eTIR technical specifications

## Technical details of message pairs I1/I2, I3/I4, I9/I10 and I11/I12

Note by the secretariat

### I. Mandate

- 1. The Inland Transport Committee (ITC), at its eighty-second session (23–28 February 2020) approved (ECE/TRANS/294, para. 84¹) the establishment of the Group of Experts on Conceptual and Technical Aspects of Computerization of the TIR Procedure (WP.30/GE.1) and endorsed its Terms of Reference (ToR)² (ECE/TRANS/WP30/2019/9 and ECE/TRANS/WP.30/2019/9/Corr.1), pending approval by the United Nations Economic Commission for Europe (ECE) Executive Committee (EXCOM). EXCOM during its remote informal meeting (20 May 2020) approved the establishment of WP.30/GE.1 until 2022, based on the ToR included in document ECE/TRANS/WP.30/2019/9 and Corr.1, as contained in document ECE/TRANS/294 (ECE/EX/2020/L.2, para. 5(b)).³
- 2. The ToR of the Group stipulate that the Group should focus its work on preparing a new version of the eTIR specifications, pending the formal establishment of the Technical Implementation Body (TIB). More specifically, the Group should (a) prepare a new version of the technical specifications of the eTIR procedure, and amendments thereto, ensuring their alignment with the functional specifications of the eTIR procedure; (b) prepare a new version of the functional specifications of the eTIR procedure, and amendments thereto, ensuring

Decision of EXCOM, ECE/EX/2020/L.2 / para. 5(b) www.unece.org/fileadmin/DAM/commission/EXCOM/Agenda/2020/Remote\_informal\_mtg\_20\_05\_ 2020/Item\_4\_ECE\_EX\_2020\_L.2\_ITC\_Sub\_bodies\_E.pdf



Decision of the Inland Transport Committee para. 84 / ECE/TRANS/294 www.unece.org/fileadmin/DAM/trans/doc/2020/itc/ECE-TRANS-294e.pdf

<sup>&</sup>lt;sup>2</sup> Terms of reference of the newly established Group approved by the Inland Transport Committee and the Executive Committee (EXCOM) of ECE

their alignment with the conceptual specifications of the eTIR procedure; (c) prepare amendments to the conceptual specifications of the eTIR procedure, upon requests by WP.30.

3. This document presents the technical details of the eTIR messages I1, I2, I3, I4, I9, I10, I11 and I12. These aspects will be part of the eTIR technical specifications document.

# II. Communication between eTIR stakeholders and the eTIR international system

### A. List of eTIR messages

### 1. Introduction

- 4. This section lists the technical details of all eTIR messages. The details, description and usage of all the fields are presented in two tables for each eTIR message. Important information is also mentioned for the eTIR stakeholders on how to use the information retrieved in the response messages and on how to prepare the several request messages that should be sent to the eTIR international system.
- 5. The structure of the following messages are defined in the relevant XSD files available on the eTIR web site<sup>4</sup> and it is important to recall that the metadata fields defined above should be present in all messages before the fields of the messages. Additional information, including examples of the eTIR messages in XML and applicable error codes, is available in the technical guides dedicated to each message pair, that are available on the eTIR web site<sup>5</sup>.

### 2. I1/I2 message pair

6. This section describes the technical specifications of the "I1 – Accept guarantee" request message sent by the customs authorities to accept a guarantee to start a TIR Transport; and the "I2 – Acceptance results" response message sent back by the eTIR international system.

<sup>&</sup>lt;sup>4</sup> See etir.org/xsd-files

<sup>&</sup>lt;sup>5</sup> See etir.org/documentation

### (a) I1 – Accept guarantee

Table 1

### I1 – field details

eTIR field name	Mapping to the XML element (XPATH)	Status	Cardinality	Format	Code lists Conditions Rules
- Message function, coded	Function	R	11	n2	CL16
- Message identifier	ID	R	11	an70	
- Type, coded	TypeCode	R	11	an3	CL26
☐ GUARANTEE	ObligationGuarantee	R	11		
- Acceptance date time	ObligationGuarantee/AcceptanceDateTime	R	11	an35	
Reference	ObligationGuarantee/ReferenceID	R	11	an35	
- Guarantee type, coded	ObligationGuarantee/SecurityDetailsCode	R	11	an3	CL12
T GUARANTEECHAIN	ObligationGuarantee/Surety	R	11		
L Code	ObligationGuarantee/Surety/ID	R	11	an35	
└┬ HOLDER	ObligationGuarantee/Principal	R	11		
<sup>L</sup> Identifier	ObligationGuarantee/Principal/ID	R	11	an35	

Table 2
I1 – field descriptions and usages

eTIR field name	Mapping to the XML element (XPATH)	Description	Usage
- Message function, coded	Function	Code describing the function of the message	The value should be set to '9' (Original)
- Message identifier	ID	Unique identifier of the message	The value should be a Globally Unique Identifier (GUID) as detailed in the dedicated section of the introduction document
- Type, coded	TypeCode	Code of the message type	The value should be set to either "I1" or "I2" depending on the message
└ GUARANTEE	ObligationGuarantee	Class representing the guarantee of this TIR transport	C .
- Acceptance date time	ObligationGuarantee/AcceptanceDateTime	Date and time of the acceptance of the guarantee by the country of departure	The value should be a date and time to be provided following the EDIFACT 208 format

eTIR field name	Mapping to the XML element (XPATH)	Description	Usage
- Reference - Guarantee type, coded	ObligationGuarantee/ReferenceID ObligationGuarantee/SecurityDetailsCode	Unique identifier of the guarantee being accepted Code of the guarantee type	CCYYMMDDHHMMSSZHHMM. For Example: 20200820145600+0100 represents 20 August 2020 at 14:56 UTC+01:00.  The value should be the unique identifier of the guarantee for this TIR transport  This value should be from the Guarantee type code (eTIR) list, and should be retrieved from a query to the eTIR international system using the I5 - Query guarantee message
├─ GUARANTEECHAIN	ObligationGuarantee/Surety	Class representing the information related to the issuing guarantee chain (providing guarantee for the TIR transport)	message
L Code	ObligationGuarantee/Surety/ID	Unique identifier of the guarantee chain which issued the guarantee	The value should be 'IRU' for guarantees issued by the International Road transport Union
└── HOLDER	ObligationGuarantee/Principal	Class representing the TIR Carnet holder (transporter) of this transport	
<sup>L</sup> Identifier	ObligationGuarantee/Principal/ID	Unique identifier of the TIR Carnet holder	The value should be the unique identifier of the TIR Carnet holder as recorded in the International TIR Data Bank (ITDB)

### (b) I2 – Acceptance results

Table 3

### I2 – field details

eTIR field name	Mapping to the XML element (XPATH)	Status	Cardinality	Format	Code lists	Conditions Rules
- Message function, coded	Function	R	11	n2	CL16	
Original Message Identifier	FunctionalReferenceID		11	an70		
- Message identifier	ID	R	11	an70		
- Type, coded	TypeCode	R	11	an3	CL26	
ERROR	Error	D	0*			C006
Error, coded	Error/ValidationCode	R	11	an8	CL99	
\ POINTER	Error/Pointer	R	1*			
Sequence number	Error/Pointer/SequenceNumeric	R	11	n5		

eTIR field name	Mapping to the XML element (XPATH)	Status	Cardinality	Format	Code lists	Conditions	Rules
<sup>L</sup> Location	Error/Pointer/Location	R	11	an512			
└ GUARANTEE	ObligationGuarantee	R	11				
<sup>L</sup> Reference	ObligationGuarantee/ReferenceID	R	11	an35			

Table 4 **I2 – field descriptions and usages** 


eTIR field name	Mapping to the XML element (XPATH)	Description	Usage
- Message function, coded	Function	Code describing the function of the message	The value should be "44" (Accepted without reserves) if the request was processed correctly. If at least one error is described in this message, the value should be"27" (Not accepted)
- Original Message Identifier	FunctionalReferenceID	Unique identifier of the request message associated with this response	The value should be the one mentioned in the message identifier field of the request message (I1)
Message identifier	ID	Unique identifier of the message	The value should be a Globally Unique Identifier (GUID) as detailed in the dedicated section of the introduction document
- Type, coded	TypeCode	Code of the message type	The value should be set to either "I1" or "I2" depending on the message
├ <del>─</del> ERROR	Error	Class representing the list of errors, if any	
- Error, coded	Error/ValidationCode	Code of the error type	The value should be the code of the error from the code list Error code (eTIR)
L_T POINTER	Error/Pointer	Class representing the pointer to the erroneous field, if any	· · · · · · · · · · · · · · · · · · ·
Sequence number	Error/Pointer/SequenceNumeric	Index of the error in the list	The value should be the 1-based index of the error in the list
Location	Error/Pointer/Location	Location of the erroneous field	The value should be the location of the erroneous field following the XPath syntax. Additional details regarding the location of the fields per error code are available on the page dedicated to errors
└ GUARANTEE	ObligationGuarantee	Class representing the guarantee of this TIR transport	
L Reference	ObligationGuarantee/ReferenceID	Unique identifier of the guarantee	The value should be the unique identifier of the guarantee for this TIR transport

- 7. The eTIR international system will return whether there were errors while processing the request message by filling in the Error list. Therefore, and as for all response messages expected from the eTIR international system, the first step when parsing the "I2 Acceptance results" response message should always be to look for potential error elements in the response message and address them accordingly as mentioned in the Error management section above.
- 8. If there are no errors listed in the response message, the national customs system should check that the reference of the guarantee that has been recorded as accepted in the eTIR international system is indeed the same as the one mentioned in the "I1 Accept guarantee" request message. If it's not the case, then customs authorities should contact the eTIR service desk to report this issue so that it can be investigated as soon as possible. If there was no error, and the response message content is as expected, the next step for the national customs systems is to send the declaration data to the eTIR international system using the "I7 Record declaration data" message.

### 3. I3/I4 message pair

- 9. This section describes the technical specifications of the "I3 Get holder information" request message sent by the customs authorities to retrieve information about a holder; and the "I4 Holder information" response message sent back by the eTIR international system.
- 10. The "I3 Get holder information" and the "I4 Holder information" form the TIR Carnet holder query system available for the customs authorities to verify the status of a TIR Carnet holder and to retrieve its information as recorded in the International TIR Data Bank (ITDB). These messages are optional for the customs authorities to implement. Although this web service is available directly in ITDB, the national customs systems can choose to access it via the eTIR international system using the "I3 Get holder information" and "I4 Holder information" messages.
- 11. It is to be noted that the "I3 Get holder information" message is also used internally by the eTIR international system for any inbound eTIR message where a holder identifier is mentioned to check its validity during the course of the TIR transport.
- 12. A holder may have different status that depends on the date, its situation toward its national customs authorities and on national transport association as well as towards the customs authority that query the information. Therefore, it is important to understand that the returned information depends on the querying customs authority as described in the figure below.

### Algorithm to determine the status of a holder



### (a) I3 – Get holder information

Table 5

### I3 – field details

eTIR field name	Mapping to the XML element (XPATH)	Status	Cardinality	Format	Code lists Conditions Rules
- Message function, coded	Function	R	11	n2	CL16
- Message identifier	ID	R	11	an70	
- Type, coded	TypeCode	R	11	an3	CL26
└── HOLDER	Principal	R	11		
<sup>L</sup> Identifier	Principal/ID	R	11	an35	

### Table 6 13 – field descriptions and usages

eTIR field name	Mapping to the XML element (XPATH)	Description	Usage
- Message function, coded	Function	Code describing the function of the message	The value should be set to "9" (Original)
Message identifier	ID	Unique identifier of the message	The value should be a Globally Unique Identifier (GUID) as detailed in the dedicated section of the introduction document
- Type, coded	TypeCode	Code of the message type	The value should be set to "I3"
└─ HOLDER	Principal	Class representing the holder	
<sup>L</sup> Identifier	Principal/ID	Unique identifier of the holder requested	The value should be the unique identifier of the holder requested, as recorded in the International TIR Data Bank (ITDB). It can be provided with or without the "/" characters.

### (b) I4 – Holder information

### Table 7

### I4 – field details

eTIR field name	Mapping to the XML element (XPATH)	Status	Cardinality	Format	Code lists	Conditions	Rules
e III jieiu nume	Mupping to the AML element (AI AIII)	Siuius	Caramany	1 Ormai	Coue usis	Conditions	Ruies

eTIR field name	Mapping to the XML element (XPATH)	Status	Cardinality	Format	Code lists	Conditions Rules
- Message function, coded	Function	R	11	n2	CL16	
- Original Message Identifier	FunctionalReferenceID	R	11	an70		
- Message identifier	ID	R	11	an70		
- Type, coded	TypeCode	R	11	an3	CL26	
ERROR	Error	D	0*			C006
- Error, coded	Error/ValidationCode	R	11	an8	CL99	
└─_ POINTER	Error/Pointer	R	1*			
- Sequence number	Error/Pointer/SequenceNumeric	R	11	n5		
L Location	Error/Pointer/Location	R	11	an512		
HOLDER	Principal	R	11			
- Name	Principal/Name	R	11	an70		
- Identifier	Principal/ID	R	11	an35		
├ <del>─</del> ADDRESS	Principal/Address	R	11			
- City name	Principal/Address/CityName	R	11	an35		
- Country, coded	Principal/Address/CountryCode	R	11	a2	CL04	
Street and number/P.O. Box	Principal/Address/Line	R	11	an256		
L Postcode identification	Principal/Address/PostcodeID	О	01	an17		
L AUTHORIZATION	Principal/AuthorizationCertificate	R	11			
- Status, coded	Principal/AuthorizationCertificate/StatusCode	R	11	an3	CL23	
ACTIVEWITHDRAWAL	Principal/AuthorizationCertificate/AuthorizationWithdrawal	O	01			
- Start date	lem:principal-AuthorizationCertificate-AuthorizationWithdrawal/Effective Date Time	R	11	an35		

eTIR field name	Mapping to the XML element (XPATH)		Cardinality	Format	Code lists	Conditions	Rules
L End date	$\label{lem:principal-Authorization} Principal/Authorization Certificate/Authorization Withdrawal/Expiration Date Time$	0	01	an35			
ACTIVEEXCLUSION	Principal/AuthorizationCertificate/Exclusion	О	0*				
- Start date	Principal/Authorization Certificate/Exclusion/Effective Date Time	R	11	an35			
- End date	Principal/Authorization Certificate/Exclusion/Expiration Date Time	O	01	an35			
L Country, coded	Principal/AuthorizationCertificate/Exclusion/CountryCode	R	11	a2	CL04		

Table 8 **I4 – field descriptions and usages** 

eTIR field name	Mapping to the XML element (XPATH)	Description	Usage
- Message function, coded	Function	Code describing the function of the message	The value should be "11" if the request was processed correctly. If at least one error is described in this message, the value should be "10"
Original Message Identifier	FunctionalReferenceID	Unique identifier of the request message associated with this response	The value should be the one mentioned in the message identifier field of the request message (13)
- Message identifier	ID	Unique identifier of the message	The value should be a Globally Unique Identifier (GUID) as detailed in the dedicated section of the introduction document
- Type, coded	TypeCode	Code of the message type	The value should be set to "I4"
ERROR	Error	Class representing the list of errors, if any	
- Error, coded	Error/ValidationCode	Code of the error type	The value should be the code of the error from the code list Error code (eTIR)
TPOINTER	Error/Pointer	Class representing the pointer to the erroneous field, if any	,
- Sequence number	Error/Pointer/SequenceNumeric	Index of the error in the list	The value should be the 1-based index of the error in the list
L Location	Error/Pointer/Location	Location of the erroneous field	The value should be the location of the erroneous field following the XPath syntax. Additional details regarding the location of the fields per error code are available on the page dedicated to errors
└─ HOLDER	Principal	Class representing the holder	the page dedicated to entits
- Name	Principal/Name	Name of the holder	The value should be the official company name, or the first and last name of the person in case of physical

eTIR field name	Mapping to the XML element (XPATH)	Description	Usage
- Identifier	Principal/ID	Unique identifier of the holder	person as recorded in the International TIR Data Bank (ITDB), to allow for quick identification The value should be the unique identifier of the holder as recorded in the International TIR Data Bank (ITDB)
├ <del>─</del> ADDRESS	Principal/Address	Class representing the physical address of the holder	as recorded in the international TIX Data Dails (11DB)
	Principal/Address/CityName	City name of the physical address of the holder	The value should be the city name of the physical address of the holder
- Country, coded	Principal/Address/CountryCode	Code of the country of the physical address of the holder	The value should be the code of the country of the physical address of the holder from the list Country name code (ISO 3166-1-alpha-2)
Street and number/P.O. Box	Principal/Address/Line	Street name of the physical address of the holder	The value should be the street name and number (or equivalent) of the physical address of the holder
L Postcode identification	Principal/Address/PostcodeID	Postal/Zip code of the physical address of the holder	The value should be the postal/ZIP code of the physical address of the holder
L AUTHORIZATION	Principal/AuthorizationCertificate	Class representing the details related to the authorization of the holder in the TIR system	
- Status, coded	Principal/AuthorizationCertificate/StatusCode	Code of the current authorization status of the holder	The value should be the code of the current authorization status of the holder from the code list Holder status (eTIR)
T ACTIVEWITHDRAWAL	Principal/AuthorizationCertificate/Authorization Withdrawal	Class representing the details related to a potential withdrawal of the holder from the TIR system	
- Start date	Principal/AuthorizationCertificate/Authorization Withdrawal/EffectiveDateTime	Start date and time of the withdrawal of the holder from the TIR system	The value should be a date to be provided following the EDIFACT 102 format CCYYMMDD . For Example: 20200820 represents 20 August 2020.
L End date	Principal/AuthorizationCertificate/Authorization Withdrawal/ExpirationDateTime	End date and time of the withdrawal of the holder from the TIR system	The value should be a date to be provided following the EDIFACT 102 format CCYYMMDD. For Example: 20200820 represents 20 August 2020.
_ ACTIVEEXCLUSION	Principal/AuthorizationCertificate/Exclusion	Class representing the list of potential exclusions of the holder in specific countries, as per Article 38 of the TIR Convention	
- Start date	Principal/AuthorizationCertificate/Exclusion/Eff ectiveDateTime	Start date and time of the exclusion of the holder from the TIR system in the country detailed in the related field below	The value should be a date to be provided following the EDIFACT 102 format CCYYMMDD. For Example: 20200820 represents 20 August 2020.
- End date	Principal/AuthorizationCertificate/Exclusion/ExpirationDateTime	End date and time of the exclusion of the holder from the TIR system in the country detailed in the related field below	The value should be a date to be provided following the EDIFACT 102 format CCYYMMDD. For Example: 20200820 represents 20 August 2020.

eTIR field name	Mapping to the XML element (XPATH)	Description	Usage
<sup>L</sup> Country, coded	Principal/AuthorizationCertificate/Exclusion/CountryCode	Code of the country in which the holder is excluded	The value should be the code of the country in which the holder is excluded from the list Country name code (ISO 3166-1-alpha-2)

- 13. The eTIR international system will return whether there were errors while processing the request message by filling in the Error list. Therefore, and as for all response messages expected from the eTIR international system, the first step when parsing the "I4 Holder information" response message should always be to look for potential error elements in the response message and address them accordingly as mentioned in the Error management section above.
- 14. If there are no errors listed in the response message, check that the Identifier of the holder is indeed the same as the one mentioned in the "I3 Get holder information" message that you sent. If it's not the case, then you should contact the eTIR service desk to report this issue so that it can be investigated as soon as possible. If everything is correct then customs authorities may focus first on the holder status code value as it reflects the holder authorization to use the TIR procedure. Additional information can then be found with the address and potential active withdrawal and active exclusions.

### 4. I9/I10 message pair

15. This section describes the technical specifications of the "I9 – Start TIR operation" request message sent by the national customs system to the eTIR international system to start a TIR operation; and the "I10 – Start results" response message sent back by the eTIR international system. This request message is sent immediately after having sent the declaration data using the "I7 – Record declaration data" message.

### (a) 19 - Start TIR operation

16. If it is the first TIR operation of the TIR transport, this message should contain all information about the seal(s) affixed to the road vehicle, the combination of vehicles or the container.

eTIR field name	Mapping to the XML element (XPATH)	Status	Cardinality	Format	Code lists	Conditions	Rules
- Message function, coded	Function	R	11	n2	CL16		
- Message identifier	ID	R	11	an70			
- Type, coded	TypeCode	R	11	an3	CL26		
└ <sub>⊤</sub> GUARANTEE	ObligationGuarantee	R	11				
- Reference	ObligationGuarantee/ReferenceID	R	11	an35			
TIROPERATION	ObligationGuarantee/TransitOperation	R	11				
- Sequence number	ObligationGuarantee/TransitOperation/SequenceNumeric	R	11	n5			
- Registration number	ObligationGuarantee/TransitOperation/RegistrationID	R	11	an35			
└── START	ObligationGuarantee/TransitOperation/OperationStart	R	11				
- End date time	Obligation Guarantee/Transit Operation/Operation Start/Inspection End Date Time	R	11	an35			
- Time limit date time	Obligation Guarantee / Transit Operation / Operation Start / Limit Date Time	O	01	an35			
ADDITIONALINFORMATION	Obligation Guarantee/Transit Operation/Operation Start/Additional Information	0	01				
L Remarks	Obligation Guarantee/Transit Operation/Operation Start/Additional Information/Content	R	11	an512			
├─ CONSIGNMENT	ObligationGuarantee/TransitOperation/OperationStart/Consignment	0	01				R007, R006, R009
│	Obligation Guarantee/Transit Operation/Operation Start/Consignment/Transport Equipment	R	1*				
- Identifier	Obligation Guarantee/Transit Operation/Operation Start/Consignment/Transport Equipment/ID	R	11	an17			

eTIR field name	Mapping to the XML element (XPATH)	Status	Cardinality	Format	Code lists	Conditions	Rules
<del> </del> SEAL	Obligation Guarantee / Transit Operation / Operation Start / Consignment / Transport Equipment / Seal	R	1*				
- Sequence number	ObligationGuarantee/TransitOperation/OperationStart/Consignment/TransportEquipment/Seal/SequenceNumeric	R	11	n5			R003, R004
- Seal number	ObligationGuarantee/TransitOperation/OperationStart/Consignment/TransportEquipment/Seal/ID	R	11	an35			R005
L Seal type, coded	Obligation Guarantee / Transit Operation / Operation Start / Consignment / Transport Equipment / Seal / Type Code	O	01	an3	CL08		
├─ CONTROL	ObligationGuarantee/TransitOperation/OperationStart/Control	R	11				
Type, coded	ObligationGuarantee/TransitOperation/OperationStart/Control/TypeCode	R	11	an3	CL25		
CONTROLRESULT	ObligationGuarantee/TransitOperation/OperationStart/Control/ControlResul t	R	11				
Result, coded	ObligationGuarantee/TransitOperation/OperationStart/Control/ControlResul t/ID	R	11	an3	CL24		
├─ NATIONALITINERARY	ObligationGuarantee/TransitOperation/OperationStart/Itinerary	О	01				
	Obligation Guarantee / Transit Operation / Operation Start / It in erary / It in erary / Operation Start / It in erary / Operation / Ope	R	11				
L Identifier	Obligation Guarantee / Transit Operation / Operation Start / It in erary / It in erary / Government Office / ID	R	11	an17			
└ CUSTOMSOFFICE	$Obligation Guarantee / Transit Operation / Operation Start / Transit Operation Start \\ Office$	R	11				
<sup>L</sup> Identifier	ObligationGuarantee/TransitOperation/OperationStart/TransitOperationStart Office/ID	R	11	an17			

Table 10 **19 – field descriptions and usages** 

eTIR field name	Mapping to the XML element (XPATH)	Description	Usage

eTIR field name	Mapping to the XML element (XPATH)	Description	Usage
- Message function, coded	Function	Code describing the function of the message	The value should be set to "9" (Original)
- Message identifier	ID	Unique identifier of the message	The value should be a Globally Unique Identifier (GUID) as detailed in the dedicated section of the introduction document
- Type, coded	TypeCode	Code of the message type	The value should be set to "I9"
☐ GUARANTEE	ObligationGuarantee	Class representing the guarantee of this TIR transport	
Reference	ObligationGuarantee/ReferenceID	Unique identifier of the guarantee	The value should be the unique identifier of the guarantee for this TIR transport
☐ TIROPERATION	ObligationGuarantee/TransitOperation	Class representing the TIR operation that is being started	
- Sequence number	ObligationGuarantee/TransitOperation/Sequence Numeric	Index of the TIR operation in the list	The value should be the 1-based index of the TIR operation in the list
- Registration number	Obligation Guarantee / Transit Operation / Registration ID	Identifier of the TIR operation	The value should be the unique identifier under which the TIR operation is nationally registered
└ <sub>⊤</sub> START	ObligationGuarantee/TransitOperation/Operation Start	Class representing the details related to the start of the TIR operation	
- End date time	$Obligation Guarantee/Transit Operation/Operation\\ Start/Inspection End Date Time$	Date and time when the TIR operation has been started	The value should be a date and time to be provided following the EDIFACT 208 format CCYYMMDDHHMMSSZHHMM. For Example: 20200820145600+0100 represents 20 August 2020 at 14:56 UTC+01:00.
- Time limit date time	ObligationGuarantee/TransitOperation/Operation Start/LimitDateTime	Date (with or without the time) by when the TIR operation should be completed	The value should be either a date only or a date and time.  If it is a date only, it should follow the EDIFACT 102 format CCYYMMDD. For Example: 20200820 represents 20 August 2020.  If it is a date and time, it should follow the EDIFACT 208 format CCYYMMDDHHMMSSZHHMM. For Example: 20200820145600+0100 represents 20 August 2020 at 14:56 UTC+01:00.
T ADDITIONALINFORMATION	ObligationGuarantee/TransitOperation/Operation Start/AdditionalInformation	Class representing the potential additional information regarding the start of the TIR operation	
L Remarks	ObligationGuarantee/TransitOperation/Operation Start/AdditionalInformation/Content	Remarks added when starting the TIR operation	The value should be the remark text a customs officer would record when starting the TIR operation

eTIR field name	Mapping to the XML element (XPATH)	Description	Usage
T CONSIGNMENT	ObligationGuarantee/TransitOperation/Operation Start/Consignment	Class representing potential parent object grouping all transport equipments and related seals information	
TRANSPORTEQUIPMENT	ObligationGuarantee/TransitOperation/Operation Start/Consignment/TransportEquipment	Class representing the list of all transport equipments used for all consignments in the TIR operation	
- Identifier	ObligationGuarantee/TransitOperation/Operation Start/Consignment/TransportEquipment/ID	Identifier of the transport equipment	The value should be marks (letters and/or numbers) which identify the transport equipment
L SEAL	ObligationGuarantee/TransitOperation/Operation Start/Consignment/TransportEquipment/Seal	Class representing the list of seals affixed to the transport equipment	
Sequence number	ObligationGuarantee/TransitOperation/Operation Start/Consignment/TransportEquipment/Seal/Seq uenceNumeric	Index of the seal in the list	The value should be the 1-based index of the seal in the list
- Seal number	ObligationGuarantee/TransitOperation/Operation Start/Consignment/TransportEquipment/Seal/ID	Unique identifier of the seal	The value should be the unique identifier of the seal affixed to the transport equipment
L Seal type, coded	ObligationGuarantee/TransitOperation/Operation Start/Consignment/TransportEquipment/Seal/Ty peCode	Code of the type of seal	The value should be the code of the type of seal from the code list Seal type (eTIR)
├─ CONTROL	ObligationGuarantee/TransitOperation/Operation Start/Control	Class representing the details of the control performed by the customs officer before starting the TIR operation	
Type, coded	ObligationGuarantee/TransitOperation/Operation Start/Control/TypeCode	Code of the type of control	The value should be the code of the type of control from the code list Control type (eTIR)
CONTROLRESULT	ObligationGuarantee/TransitOperation/Operation Start/Control/ControlResult	Class representing the details of the outcome of the control performed by the customs officer	
Result, coded	ObligationGuarantee/TransitOperation/Operation Start/Control/ControlResult/ID	Code of the result of the control	The value should be the code of the result of the control from the code list Control result (eTIR)
T NATIONALITINERARY	ObligationGuarantee/TransitOperation/Operation Start/Itinerary	Class representing the potential national itinerary that has to be followed by the TIR transport, mentioning one or more customs offices to be visited	

eTIR field name	Mapping to the XML element (XPATH)	Description	Usage
\_T NATIONALITINERARYCUSTOMSOF FICE	ObligationGuarantee/TransitOperation/Operation Start/Itinerary/ItineraryGovernmentOffice	Class representing the details identifying a customs office that has to be visited by the TIR transport during its itinerary	
L Identifier	ObligationGuarantee/TransitOperation/Operation Start/Itinerary/ItineraryGovernmentOffice/ID	Unique identifier of the customs office of the itinerary	The value should be the unique identifier of the customs office of the itinerary. This identifier is the one recorded in the International TIR Data Bank (ITDB) for the customs office
└── CUSTOMSOFFICE	ObligationGuarantee/TransitOperation/Operation Start/TransitOperationStartOffice	Class representing the details of the customs office where the TIR operation started	
<sup>L</sup> Identifier	ObligationGuarantee/TransitOperation/Operation Start/TransitOperationStartOffice/ID	Unique identifier of the customs office where the TIR operation is started	The value should be the unique identifier of the customs office where the TIR operation is started. This identifier is the one recorded in the International TIR Data Bank (ITDB) for the customs office

### (b) I10 – Start results

Table 11
I10 – field details

eTIR field name	Mapping to the XML element (XPATH)	Status	Cardinality	Format	Code lists	Conditions	Rules
Message function, coded	Function	R	11	n2	CL16		
- Original Message Identifier	FunctionalReferenceID	R	11	an70			
- Message identifier	ID	R	11	an70			
- Type, coded	TypeCode	R	11	an3	CL26		
ERROR	Error	D	0*			C006	
Ferror, coded	Error/ValidationCode	R	11	an8	CL99		
¬ POINTER	Error/Pointer	R	1*				
- Sequence number	Error/Pointer/SequenceNumeric	R	11	n5			
Location	Error/Pointer/Location	R	11	an512			
└ GUARANTEE	ObligationGuarantee	R	11				
- Status, coded	ObligationGuarantee/StatusCode	R	11	an3	CL22		

eTIR field name	Mapping to the XML element (XPATH)	Status	Cardinality	Format	Code lists	Conditions	Rules
- Reference	ObligationGuarantee/ReferenceID	R	11	an35			
TIROPERATION	ObligationGuarantee/TransitOperation	R	11				
- Sequence number	ObligationGuarantee/TransitOperation/SequenceNumeric	R	11	n5			
- Registration number	ObligationGuarantee/TransitOperation/RegistrationID	R	11	an35			
└── START	ObligationGuarantee/TransitOperation/OperationStart	R	11				
L End date time	Obligation Guarantee / Transit Operation / Operation Start / Inspection End Date Time	R	11	an35			
└┬ HOLDER	ObligationGuarantee/Principal	R	11				
- Identifier	ObligationGuarantee/Principal/ID	R	11	an35			
T AUTHORIZATION	ObligationGuarantee/Principal/AuthorizationCertificate	R	11				
- Status, coded	ObligationGuarantee/Principal/AuthorizationCertificate/StatusCode	R	11	an3	CL23		
T ACTIVEWITHDRAWAL	Obligation Guarantee/Principal/Authorization Certificate/Authorization Withdrawal	0	01				
- Start date	Obligation Guarantee / Principal / Authorization Certificate / Authorization With drawal / Effective Date Time	R	11	an35			
L End date	Obligation Guarantee/Principal/Authorization Certificate/Authorization Withdrawal/Expiration Date Time	O	01	an35			
ACTIVEEXCLUSION	ObligationGuarantee/Principal/AuthorizationCertificate/Exclusion	O	0*				
- Start date	ObligationGuarantee/Principal/AuthorizationCertificate/Exclusion/Effective DateTime	R	11	an35			
- End date	ObligationGuarantee/Principal/AuthorizationCertificate/Exclusion/ExpirationDateTime	O	01	an35			
L Country, coded	ObligationGuarantee/Principal/AuthorizationCertificate/Exclusion/CountryCode	R	11	a2	CL04		

Table 12 **I10** – field descriptions and usages

eTIR field name	Mapping to the XML element (XPATH)	Description	Usage
- Message function, coded	Function	Code describing the function of the message	The value should be "44" (Accepted without reserves) if the request was processed without error, else, in case of error(s) reported in this message, the value should be"27" (Not accepted)
- Original Message Identifier	FunctionalReferenceID	Unique identifier of the request message associated with this response	The value should be the one mentioned in the message identifier field of the request message (I9)
- Message identifier	ID	Unique identifier of the message	The value should be a Globally Unique Identifier (GUID) as detailed in the dedicated section of the introduction document
- Type, coded	TypeCode	Code of the message type	The value should be set to "I10"
├ <del>─</del> ERROR	Error	Class representing the list of errors, if any	
Frror, coded	Error/ValidationCode	Code of the error type	The value should be the code of the error from the list Error code (eTIR)
L POINTER	Error/Pointer	Class representing the pointer to the erroneous field, if any	
- Sequence number	Error/Pointer/SequenceNumeric	Index of the error in the list	The value should be the 1-based index of the error in the list
L Location	Error/Pointer/Location	Location of the erroneous field	The value should be the location of the erroneous field following the XPath syntax. Additional details regarding the location of the fields per error code are available on the page dedicated to errors
└ GUARANTEE	ObligationGuarantee	Class representing the guarantee of this TIR transport	
- Status, coded	ObligationGuarantee/StatusCode	Current status of the guarantee	The value should be the code of the status of the guarantee from the code list Guarantee status (eTIR)
- Reference	ObligationGuarantee/ReferenceID	Unique identifier of the guarantee	The value should be the unique identifier of the guarantee for this TIR transport
TIROPERATION	ObligationGuarantee/TransitOperation	Class representing the TIR operation that is being started	
- Sequence number	ObligationGuarantee/TransitOperation/Sequence Numeric	Index of the TIR operation in the list	The value should be the 1-based index of the TIR operation in the list
	ObligationGuarantee/TransitOperation/RegistrationID	Identifier of the TIR operation	The value should be the unique identifier under which the TIR operation is nationally registered
└┬ START	ObligationGuarantee/TransitOperation/Operation Start	Class representing the details related to the start of the TIR operation	
L End date time	ObligationGuarantee/TransitOperation/Operation Start/InspectionEndDateTime	Date and time when the TIR operation has been started	The value should be a date and time to be provided following the EDIFACT 208 format CCYYMMDDHHMMSSZHHMM. For Example:

eTIR field name	Mapping to the XML element (XPATH)	Description	Usage
			20200820145600+0100 represents 20 August 2020 at 14:56 UTC+01:00.
└─ HOLDER	ObligationGuarantee/Principal	Class representing the holder (transporter) of this transport	
- Identifier	ObligationGuarantee/Principal/ID	Unique identifier of the holder	The value should be the unique identifier of the holder as recorded in the International TIR Data Bank (ITDB)
☐ AUTHORIZATION	ObligationGuarantee/Principal/AuthorizationCert ificate	TIR system	
- Status, coded	ObligationGuarantee/Principal/AuthorizationCert ificate/StatusCode	Code of the current authorization status of the holder	The value should be the code of the current authorization status of the holder from the code list Holder status (eTIR)
T ACTIVEWITHDRAWAL	ObligationGuarantee/Principal/AuthorizationCert ificate/AuthorizationWithdrawal	Class representing the details related to a potential withdrawal of the holder from the TIR system	
- Start date	ObligationGuarantee/Principal/AuthorizationCert ificate/AuthorizationWithdrawal/EffectiveDateTi me	Start date of the withdrawal of the holder from the TIR system	The value should be a date to be provided following the EDIFACT 102 format CCYYMMDD. For Example: 20200820 represents 20 August 2020.
L End date	ObligationGuarantee/Principal/AuthorizationCert ificate/AuthorizationWithdrawal/ExpirationDate Time	End date of the withdrawal of the holder from the TIR system	The value should be a date to be provided following the EDIFACT 102 format CCYYMMDD. For Example: 20200820 represents 20 August 2020.
☐ ACTIVEEXCLUSION	ObligationGuarantee/Principal/AuthorizationCert ificate/Exclusion	Class representing the list of potential exclusions of the holder in specific countries, as per Article 38 of the TIR Convention	
- Start date	ObligationGuarantee/Principal/AuthorizationCert ificate/Exclusion/EffectiveDateTime	Start date of the exclusion of the holder from the TIR system in the country detailed in the related field below	The value should be a date to be provided following the EDIFACT 102 format CCYYMMDD. For Example: 20200820 represents 20 August 2020.
- End date	ObligationGuarantee/Principal/AuthorizationCert ificate/Exclusion/ExpirationDateTime	End date of the exclusion of the holder from the TIR system in the country detailed in the related field below	The value should be a date to be provided following the EDIFACT 102 format CCYYMMDD. For Example: 20200820 represents 20 August 2020.
L Country, coded	ObligationGuarantee/Principal/AuthorizationCert ificate/Exclusion/CountryCode	Code of the country in which the holder is excluded	The value should be the code of the country in which the holder is excluded from the list Country name code (ISO 3166-1-alpha-2)

- 17. The eTIR international system will return whether there were errors while processing the request message by filling in the Error list. Therefore, and as for all response messages expected from the eTIR international system, the first step when parsing the "I10 Start results" response message should always be to look for potential error elements in the response message and address them accordingly as mentioned in the Error management section above.
- 18. If there was no error, and the response message content is as expected, the next step for the national customs systems is to authorize the holder to start his journey across the country (the TIR operation).

### 5. I11/I12 message pair

19. This section describes the technical specifications of the "I11 – Terminate TIR operation" request message sent by the national customs system to terminate (complete) a TIR operation; and the "I11 – Termination results" response message sent back by the eTIR international system.

### (a) I11 – Terminate TIR operation

Table 13

### I11 – field details

eTIR field name	Mapping to the XML element (XPATH)	Status	Cardinality	Format	Code lists	Conditions	Rules
- Message function, coded	Function	R	11	n2	CL16		
- Message identifier	ID	R	11	an70			
- Type, coded	TypeCode	R	11	an3	CL26		
└ GUARANTEE	ObligationGuarantee	R	11				
- Reference	ObligationGuarantee/ReferenceID	R	11	an35			
TIROPERATION	ObligationGuarantee/TransitOperation	R	11				
- Sequence number	ObligationGuarantee/TransitOperation/SequenceNumeric	R	11	n5			
- Registration number	ObligationGuarantee/TransitOperation/RegistrationID	R	11	an35			
TERMINATION	ObligationGuarantee/TransitOperation/OperationTermination	R	11				
- End date time	Obligation Guarantee / Transit Operation / Operation Termination / Inspection End Date Time	R	11	an35			
- Number of packages	Obligation Guarantee/Transit Operation/Operation Termination/Package Quantity	R	11	n8			
- Termination type, coded	Obligation Guarantee / Transit Operation / Operation Termination / Type Code	R	11	an3	CL27		
☐ ADDITIONALINFORMATION	Obligation Guarantee / Transit Operation / Operation Termination / Additional Information	0	01				
L Reservations	Obligation Guarantee/Transit Operation/Operation Termination/Additional Information/Content	R	11	an512			
T CONSIGNMENT	ObligationGuarantee/TransitOperation/OperationTermination/Consignment	О	01				R007, R006
│ └── TRANSPORTEQUIPMENT	ObligationGuarantee/TransitOperation/OperationTermination/Consignment/ TransportEquipment	R	1*				

eTIR field name	Mapping to the XML element (XPATH)	Status	Cardinality	Format	Code lists	Conditions	Rules
- Identifier	ObligationGuarantee/TransitOperation/OperationTermination/Consignment/ TransportEquipment/ID			an17			
L <sub>T</sub> SEAL	Obligation Guarantee/Transit Operation/Operation Termination/Consignment/Transport Equipment/Seal	R	1*				
Sequence number	ObligationGuarantee/TransitOperation/OperationTermination/Consignment/ TransportEquipment/Seal/SequenceNumeric	R	11	n5			R003, R004
- Seal number	ObligationGuarantee/TransitOperation/OperationTermination/Consignment/TransportEquipment/Seal/ID	R	11	an35			R005
L Seal type, coded	ObligationGuarantee/TransitOperation/OperationTermination/Consignment/TransportEquipment/Seal/TypeCode	O	01	an3	CL08		
├─ CONTROL	ObligationGuarantee/TransitOperation/OperationTermination/Control	R	11				
Type, coded	$Obligation Guarantee / Transit Operation / Operation Termination / Control / Type \\ Code$	R	11	an3	CL25		
CONTROLRESULT	Obligation Guarantee / Transit Operation / Operation Termination / Control	R	11				
L Result, coded	Obligation Guarantee / Transit Operation / Operation Termination / Control / Control Result / ID	R	11	an3	CL24		
CUSTOMSOFFICE	Obligation Guarantee / Transit Operation / Operation Termination / Transit Operation Termination Of fice	R	11				
L Identifier	Obligation Guarantee / Transit Operation / Operation Termination / Transit Operation Termination Office / ID	R	11	an17			

Table 14
I11 – field descriptions and usages

eTIR field name	Mapping to the XML element (XPATH)	Description	Usage
- Message function, coded	Function	Code describing the function of the message	The value should be set to "9" (Original)
- Message identifier	ID	Unique identifier of the message	The value should be a Globally Unique Identifier (GUID) as detailed in the dedicated section of the introduction document

eTIR field name	Mapping to the XML element (XPATH)	Description	Usage
- Type, coded	TypeCode	Code of the message type	The value should be set to "I11"
☐ GUARANTEE	ObligationGuarantee	Class representing the guarantee of this TIR transport	
- Reference	ObligationGuarantee/ReferenceID	Unique identifier of the guarantee	The value should be the unique identifier of the guarantee for this TIR transport
T TIROPERATION	ObligationGuarantee/TransitOperation	Class representing the TIR operation that is being terminated	guarantee for time first transport
- Sequence number	ObligationGuarantee/TransitOperation/Sequence Numeric	Index of the TIR operation in the list	The value should be the 1-based index of the TIR operation in the list
- Registration number	ObligationGuarantee/TransitOperation/RegistrationID	Identifier of the TIR operation	The value should be the unique identifier of the TIR operation
☐ TERMINATION	ObligationGuarantee/TransitOperation/Operation Termination	Class representing the details related to the termination of the TIR operation	
- End date time	ObligationGuarantee/TransitOperation/Operation Termination/InspectionEndDateTime	Date and time when the TIR operation has just been terminated	The value should be a date and time to be provided following the EDIFACT 208 format CCYYMMDDHHMMSSZHHMM. For Example: 20200820145600+0100 represents 20 August 2020 at 14:56 UTC+01:00.
- Number of packages	ObligationGuarantee/TransitOperation/Operation Termination/PackageQuantityQuantity	Number of packages unloaded	The value should be the number of packages unloaded during the termination of the TIR operation
- Termination type, coded	ObligationGuarantee/TransitOperation/Operation Termination/TypeCode	Code of the type of termination of the TIR operation	The value should be the type of termination code of the TIR operation from the code list Termination type (eTIR)
T ADDITIONALINFORMATION	ObligationGuarantee/TransitOperation/Operation Termination/AdditionalInformation	Class representing potential additional information regarding the termination of the TIR operation	
L Reservations	ObligationGuarantee/TransitOperation/Operation Termination/AdditionalInformation/Content	Reservations added when terminating the TIR operation	The value should be the reservations or remarks a customs officer would record when terminating the TIR operation
T CONSIGNMENT	ObligationGuarantee/TransitOperation/Operation Termination/Consignment	Class representing potential parent object grouping details about all transport equipments and related seals information	
│ └┬ TRANSPORTEQUIPMENT	ObligationGuarantee/TransitOperation/Operation Termination/Consignment/TransportEquipment	Class representing the list of all transport equipments used for all consignments in the TIR operation	

eTIR field name	Mapping to the XML element (XPATH)	Description	Usage
- Identifier	ObligationGuarantee/TransitOperation/Operation Termination/Consignment/TransportEquipment/I D		The value should be the marks (letters and/or numbers) which identify the transport equipment
<del> </del> SEAL	ObligationGuarantee/TransitOperation/Operation Termination/Consignment/TransportEquipment/ Seal	Class representing the list of seals affixed to the transport equipment	
- Sequence number	ObligationGuarantee/TransitOperation/Operation Termination/Consignment/TransportEquipment/ Seal/SequenceNumeric	Index of the seal in the list	The value should be the 1-based index of the seal in the list
- Seal number	ObligationGuarantee/TransitOperation/Operation Termination/Consignment/TransportEquipment/ Seal/ID	Unique identifier of the seal	The value should be the unique identifier of the seal affixed to the transport equipment
L Seal type, coded	ObligationGuarantee/TransitOperation/Operation Termination/Consignment/TransportEquipment/ Seal/TypeCode	Code of the type of seal	The value should be the code of the type of seal from the code list Seal type (eTIR)
├── CONTROL	ObligationGuarantee/TransitOperation/Operation Termination/Control	Class representing the details of the control performed by the customs officer while terminating the TIR operation	
Type, coded	ObligationGuarantee/TransitOperation/Operation Termination/Control/TypeCode	a 1 c1 . c . 1	The value should be the code of the type of control from the code list Control type (eTIR)
CONTROLRESULT	ObligationGuarantee/TransitOperation/Operation Termination/Control/ControlResult	Class representing the details of the outcome of the control performed by the customs officer	
Result, coded	ObligationGuarantee/TransitOperation/Operation Termination/Control/ControlResult/ID	Code of the result of the control	The value should be the code of the result of the control from the code list Control result (eTIR)
☐ CUSTOMSOFFICE	ObligationGuarantee/TransitOperation/Operation Termination/TransitOperationTerminationOffice	Class representing the details of the customs office where the TIR operation is terminated	
L Identifier	ObligationGuarantee/TransitOperation/Operation Termination/TransitOperationTerminationOffice/ ID	Unique identifier of the customs office where the TIR operation is terminated	The value should be the unique identifier of the customs office where the TIR operation is terminated. This identifier is the one recorded in the International TIR Data Bank (ITDB) for the customs office

### (b) I12 – Termination results

Table 15
I12 – field details

eTIR field name	Mapping to the XML element (XPATH)	Status	Cardinality	Format	Code lists	Conditions	Rules
- Message function, coded	Function	R	11	n2	CL16		
- Original Message Identifier	FunctionalReferenceID	R	11	an70			
- Message identifier	ID	R	11	an70			
- Type, coded	TypeCode	R	11	an3	CL26		
ERROR	Error	D	0*			C006	
- Error, coded	Error/ValidationCode	R	11	an8	CL99		
\_T POINTER	Error/Pointer	R	1*				
- Sequence number	Error/Pointer/SequenceNumeric	R	11	n5			
Location	Error/Pointer/Location	R	11	an512			
☐ GUARANTEE	ObligationGuarantee	R	11				
- Status, coded	ObligationGuarantee/StatusCode	R	11	an3	CL22		
- Reference	ObligationGuarantee/ReferenceID	R	11	an35			
TIROPERATION	ObligationGuarantee/TransitOperation	R	11				
- Sequence number	ObligationGuarantee/TransitOperation/SequenceNumeric	R	11	n5			
- Registration number	ObligationGuarantee/TransitOperation/RegistrationID	R	11	an35			
<del> </del> TERMINATION	ObligationGuarantee/TransitOperation/OperationTermination	R	11				
L End date time	$Obligation Guarantee / Transit Operation / Operation Termination / Inspection End \\ Date Time$	R	11	an35			
└┬ HOLDER	ObligationGuarantee/Principal	R	11				
- Identifier	ObligationGuarantee/Principal/ID	R	11	an35			

eTIR field name	Mapping to the XML element (XPATH)	Status	Cardinality	Format	Code lists	Conditions	Rules
L AUTHORIZATION	ObligationGuarantee/Principal/AuthorizationCertificate	R	11				
- Status, coded	ObligationGuarantee/Principal/AuthorizationCertificate/StatusCode	R	11	an3	CL23		
ACTIVEWITHDRAWAL	Obligation Guarantee / Principal / Authorization Certificate / Authorization With drawal	O	01				
- Start date	Obligation Guarantee / Principal / Authorization Certificate / Authorization With drawal / Effective Date Time	R	11	an35			
L End date	Obligation Guarantee / Principal / Authorization Certificate / Authorization With drawal / Expiration Date Time	O	01	an35			
_ ACTIVEEXCLUSION	ObligationGuarantee/Principal/AuthorizationCertificate/Exclusion	O	0*				
- Start date	$Obligation Guarantee / Principal / Authorization Certificate / Exclusion / Effective \\ Date Time$	R	11	an35			
- End date	Obligation Guarantee / Principal / Authorization Certificate / Exclusion / Expiration Date Time	O	01	an35			
L Country, coded	Obligation Guarantee / Principal / Authorization Certificate / Exclusion / Country Code	R	11	a2	CL04		

Table 16
I12 – field descriptions and usages

eTIR field name	Mapping to the XML element (XPATH)	Description	Usage
- Message function, coded	Function	Code describing the function of the message	The value should be "44" (Accepted without reserves) if the request was processed correctly. If at least one error is described in this message, the value should be"27" (Not accepted)
- Original Message Identifier	FunctionalReferenceID	Unique identifier of the request message associated with this response	The value should be the one mentioned in the message identifier field of the request message (I11)
- Message identifier	ID	Unique identifier of the message	The value should be a Globally Unique Identifier (GUID) as detailed in the dedicated section of the introduction document
- Type, coded	TypeCode	Code of the message type	The value should be set to "I12"
├ <del>─</del> ERROR	Error	Class representing the list of errors, if any	

eTIR field name	Mapping to the XML element (XPATH)	Description	Usage
- Error, coded	Error/ValidationCode	Code of the error type	The value should be the code of the error from the code list Error code (eTIR)
¬ POINTER	Error/Pointer	Class representing the pointer to the erroneous field, if any	not Enter code (CTIIC)
Sequence number	Error/Pointer/SequenceNumeric	Index of the error in the list	The value should be the 1-based index of the error in the list
Location	Error/Pointer/Location	Location of the erroneous field	The value should be the location of the erroneous field following the XPath syntax. Additional details regarding the location of the fields per error code are available on the page dedicated to errors
└ GUARANTEE	ObligationGuarantee	Class representing the guarantee of this TIR transport	
- Status, coded	ObligationGuarantee/StatusCode	Current status of the guarantee	The value should be the code of the status of the guarantee from the code list Guarantee status (eTIR)
Reference	ObligationGuarantee/ReferenceID	Unique identifier of the guarantee	The value should be the unique identifier of the guarantee for this TIR transport
TIROPERATION	ObligationGuarantee/TransitOperation	Class representing the TIR operation that is being terminated	
Sequence number	ObligationGuarantee/TransitOperation/Sequence Numeric	Index of the TIR operation in the list	The value should be the 1-based index of the TIR operation in the list
	ObligationGuarantee/TransitOperation/RegistrationID	Identifier of the TIR operation	The value should be the unique identifier of the TIR operation
<del> </del> TERMINATION	ObligationGuarantee/TransitOperation/Operation Termination	Class representing the details related to the termination of the TIR operation	
L End date time	ObligationGuarantee/TransitOperation/Operation Termination/InspectionEndDateTime	Date and time when the TIR operation has been terminated	The value should be a date and time to be provided following the EDIFACT 208 format CCYYMMDDHHMMSSZHHMM. For Example: 20200820145600+0100 represents 20 August 2020 at 14:56 UTC+01:00.
└── HOLDER	ObligationGuarantee/Principal	Class representing the holder (transporter) of this transport	
- Identifier	ObligationGuarantee/Principal/ID	Unique identifier of the holder	The value should be the unique identifier of the holder as recorded in the International TIR Data Bank (ITDB)
☐ AUTHORIZATION	ObligationGuarantee/Principal/AuthorizationCert ificate	Class representing the details related to the authorization of the holder in the TIR system	()
- Status, coded	ObligationGuarantee/Principal/AuthorizationCert ificate/StatusCode	Code of the current authorization status of the holder	The value should be the code of the current authorization status of the holder from the code list Holder status (eTIR)

TIR field name	Mapping to the XML element (XPATH)	Description	Usage
ACTIVEWITHDRAWAL	ObligationGuarantee/Principal/AuthorizationCert ificate/AuthorizationWithdrawal	Class representing the details related to a potential withdrawal of the holder from the TIR system	
- Start date	ObligationGuarantee/Principal/AuthorizationCert ificate/AuthorizationWithdrawal/EffectiveDateTi me	Start date of the withdrawal of the holder from the TIR system	The value should be a date to be provided following the EDIFACT 102 format CCYYMMDD. For Example: 20200820 represents 20 August 2020.
L End date	ObligationGuarantee/Principal/AuthorizationCert ificate/AuthorizationWithdrawal/ExpirationDate Time	End date of the withdrawal of the holder from the TIR system	The value should be a date to be provided following the EDIFACT 102 format CCYYMMDD. For Example: 20200820 represents 20 August 2020.
☐ ACTIVEEXCLUSION	ObligationGuarantee/Principal/AuthorizationCert ificate/Exclusion	Class representing the list of potential exclusions of the holder in specific countries, as per Article 38 of the TIR Convention	
- Start date	ObligationGuarantee/Principal/AuthorizationCert ificate/Exclusion/EffectiveDateTime	Start date of the exclusion of the holder from the TIR system in the country detailed in the related field below	The value should be a date to be provided following the EDIFACT 102 format CCYYMMDD. For Example: 20200820 represents 20 August 2020.
- End date	ObligationGuarantee/Principal/AuthorizationCert ificate/Exclusion/ExpirationDateTime	End date of the exclusion of the holder from the TIR system in the country detailed in the related field below	The value should be a date to be provided following the EDIFACT 102 format CCYYMMDD. For Example: 20200820 represents 20 August 2020.
<sup>L</sup> Country, coded	ObligationGuarantee/Principal/AuthorizationCert ificate/Exclusion/CountryCode	Code of the country in which the holder is excluded	The value should be the code of the country in which the holder is excluded from the list Country name code (ISO 3166-1-alpha-2)

- 20. The eTIR international system will return whether there were errors while processing the request message by filling in the Error list. Therefore, and as for all response messages expected from the eTIR international system, the first step when parsing the "I12 Termination results" response message should always be to look for potential error elements in the response message and address them accordingly as mentioned in the Error management section above.
- 21. If there was no error, and the response message content is as expected, the next step for the national customs systems is to discharge the TIR operation by sending the "I13 Discharge TIR operation" message to the eTIR international system.