
01-00 IR-TR-BG-RO Main Process
IR-TR border
TR-BG border
BG-RO border
Holder
Iran eTIR
Turkey eTIR
eTIR International system
Bulgaria NCTS
Romania NCTS
Send advance TIR data (ATD)
Present vehicle and goods at Departure
Accompanying document
Goods move
Present goods at eTIR Exit
Cross border
Present goods at eTIR Entry
Goods move
Present goods at eTIR Exit
Cross border
Present goods at NCTS Departure/ eTIR Entry
Goods move
Present goods at Final Destination
End
Advance TIR data (E9)
Process and store ATD
Documentary and physical controls
Results OK
01-01 Process Accept guarantee
01-02 Process Accept declaration
Notify Start of operation
Print accompanying document
01-04 Process Presentation at eTIR Exit
Query guarantee (I5)/ Query results (I6)
Receive Declaration Data (DD)
01-05 Process Presentation at eTIR Entry
01-06 Process Presentation at eTIR Exit
Extract and return Guaratee data
Change guarantee status to "in use" and return result
Receive Declaration Data (DD)
01-03 Process Start of operation
Notify termination and discharge of operation
Notify start of operation
Notify termination and discharge of operation
Notify start of operation
Notify termination and discharge of operation
Receive pre-lodged declaration
01-07 Process Presentation at NCTS Departure/ eTIR Entry
01-08 Process Presentation at Final Destination


01-01 Process Accept guarantee
Customs Administration using eTIR
eTIR international system
Send guarantee acceptance
Accept declaration
Acceptance relusts (I2)
Accept guarantee (I1)
Return results
Change guarantee status to «in use»

01-02 Process Accept declaration



01-03 Process Start of operation



01-04 Process Presentation at eTIR Exit

Holder

Present goods at eTIR Exit

Cross border

Present goods at Entry/Departure

Customs Administration using eTIR

Discharge

Documentary [and physical] controls

Results OK

Notify termination of operation

Notify discharge of operation

Terminate TIR operation (I11)/ Termination results (I12)

Discharge TIR operation (I13)/ Discharge results (I14)

eTIR international system

Notification confirmation (I16)

Store termination of TIR operation info

If seals have been changed

Notify subsequent countries

Notify customs (I15)

Store discharge of TIR operation info

01-09 Notify guarantee chain

01-09 Notify guarantee chain

Notify customs (I15) Termination information (incl. Seals) and declaration data

Notification confirmation (I16)

Subsequent Customs Administration using eTIR

Receive seals

Process and store seals

Documentary [and physical] control

NCTS eTIR Converter

Respond

Process eTIR declaration data

IE013 Declaration amendment

Customs office of Departure NCTS

IE928 Positive acknowledge

Process pre-lodged declaration

Process declaration data

01-05 Process Presentation at eTIR Entry



01-06 Process Presentation at eTIR Exit




01-07 Process Presentation at NCTS Departure/eTIR Entry
Holder
eTIR international system
NCTS eTIR Converter
Customs office of Departure NCTS
Customs office of Destination NCTS
Present goods at NCTS Departure/eTIR Entry
Goods move
Present goods at Final Destination
Store start TIR operation info
01-09 Notify guarantee chain
IE170
Presentation notification
Start of operation (I9)/
Start results (I10)
Notify start of operation
IE029
Release into transit
IE028
Allocation of MRN
IE029
Release into transit
Process pre-lodged declaration data
Process declaration data
Accept declaration
Documentary [and physical] controls
Release into transit
IE001
Advanced arrival record
Receive Advanced arrival record

01-08 Process Presentation at Final Destination




01-09 Process Notify guarantee chain
eTIR international system
eTIR guarantee chain
Notify guarantee chain
Notify guarantee chain (E7)/
Norification confirmation (E8)
Process and store data